

# SecurityCenter Key Upload


If SecurityCenter is already installed and the setup wizard completed, save the key file to the local hard drive of the system you will be using to access SecurityCenter via a web browser and follow the steps below.

You will need to obtain a key from Tenable Network Security in order to start the key upload process. Refer to the following document for information on submitting your hostname to obtain your key:


[http://static.tenable.com/documentation/Key\\_Request\\_Help.pdf](http://static.tenable.com/documentation/Key_Request_Help.pdf)

**Step 1** – Save the .key file to your workstation and note its location.


**Step 2** – Log in to SecurityCenter as admin.




**Step 3** – Click on the small text “System” in the upper right corner of the screen.



Step 4 – From the drop-down menu select “Configuration”.



Step 5 – Click “License” next to the License File field.



Step 6 – Click “Update License”.

SecurityCenter License

IP Limit

Type Demo

Expiration

Licensee Company Name Here

Hostname

License File Valid Update License

Step 7 – Click “Choose File”, then browse to where you saved the license key locally, select it, click “Open”, and then “Upload”.

Licensee Company Name Here

Hostname

License File Choose File Cancel

Step 8 – Allow SecurityCenter a moment to process the file, and make sure the Status shows “Valid” in green letters under the license field.


Licensee Company Name Here

Hostname

License File Valid license


## Maintenance Activation Code Registration

To obtain your Activation Code, log in to the Tenable Support Portal at <https://support.tenable.com> and then click on "Activation Codes". Select the "+" next to the appropriate product. The product Activation Code will be displayed.




To register the Activation Code, log in to the SecurityCenter 5.x console as the Admin account.


**Step 1** - Click on the "+" next to Nessus.



**Step 2** - Enter the Maintenance Activation Code in the provided area next to the "Nessus Activation Code" field, and then click "Register".



Note: A green valid message will appear when the Maintenance Activation Code is registered.





For more detailed set up instructions for SecurityCenter, refer to the SecurityCenter user guide. You can access this guide by logging into the Tenable Support Portal at <https://support.tenable.com> and then click on Downloads → Product Documentation → SecurityCenter → SecurityCenter HTML Guide.

For technical questions regarding SecurityCenter, contact [support@tenable.com](mailto:support@tenable.com).

Read more about Tenable Support Portal here:

[http://www.tenable.com/whitepapers/Tenable\\_Support\\_Portal\\_Features.pdf](http://www.tenable.com/whitepapers/Tenable_Support_Portal_Features.pdf)

## About Tenable Network Security

Tenable Network Security provides continuous network monitoring to identify vulnerabilities, reduce risk, and ensure compliance. Our family of products includes SecurityCenter Continuous View™, which provides the most comprehensive and integrated view of network health, and Nessus®, the global standard in detecting and assessing network data. Tenable is relied upon by many of the world's largest corporations, not-for-profit organizations and public sector agencies, including the entire U.S. Department of Defense. For more information, visit [tenable.com](http://tenable.com).